



The Center for Astrophysical Thermonuclear Flashes

FLASH3 Infrastructure Units I

Flash Tutorial
June 22, 2009
Dr. Klaus Weide



An Advanced Simulation & Computing (ASC)
Academic Strategic Alliance Program (ASAP) Center
at The University of Chicago





Infrastructure I Topics

❑ Driver Unit

- ❑ Overview and Function
- ❑ Unsplit vs Split

❑ Grid Unit

- ❑ Overview: Implementations
- ❑ Overview: blocks, cells,
- ❑ PARAMESH: oct-tree
- ❑ Data structures and Meta-Data
- ❑ Configuring Variables for Grid Data Structures
- ❑ Dimensions and Geometries
- ❑ What the Grid Code Unit Actually Does
- ❑ Using Grid



Driver Unit

- ❑ Overview and Function
- ❑ Unsplit vs Split



Driver - Overview and Function

All other units and their subroutines are called, directly or indirectly, from *Driver*. There are three phases encompassing everything FLASH does:

Initialize – Simulate (and probably produce some output) – Finish

The main F90 program, `Flash.F90`, invokes the rest of the code like this:

- ❑ call `Driver_initFlash`
 - ❑ Initialize parameters, data, Grid incl. variable values, ...
- ❑ call `Driver_evolveFlash`
 - ❑ Advance in time (the only kind of “evolution” that FLASH does)
- ❑ call `Driver_finalizeFlash`
 - ❑ Clean up nicely



Time Evolution - Unsplit and Split

- ❑ FLASH3 provides two variants of time evolution (two *Driver* “implementations”): *Split* and *Unsplit*.
 - ❑ Pick the right one for the *Hydro* implementation used (normally this is automatically done by including the *Hydro* implementation)
 - ❑ `Driver_evolveFlash` implements the main loop of FLASH3.
 - ❑ The loop ends normally when one of several conditions is satisfied:
 - ❑ Loop counter `dr_nstep = nstart ... nend`
 - ❑ Simulation time reaches `tmax`
 - ❑ Wall clock reaches `wall_clock_time_limit`
 - ❑ Time step `dt` can vary between `dtmin` and `dtmax`, `Driver_computeDt` computes new `dt` after each loop iteration.
 - ❑ `Driver_computeDt` calls `Hydro_computeDt`, `Particles_computeDt`, etc. to honor time step requirements of different code units.



Time Evolution - Unsplit vs Split

- DriverMain/Split/
Driver_evolveFlash loop for **split** *Hydro* (PPM, default)

```
Do ...  
  call Hydro(...,SWEEP_XYZ)  
  call other physics  
  .....  
  call Hydro(...,SWEEP_ZYX)  
  call other physics  
  .....  
End Do
```

- Each loop iteration advances the solution by **2 dt**

- DriverMain/Unsplit/
Driver_evolveFlash loop for **unsplit** *Hydro* (staggered mesh MHD etc.)

```
Do ...  
  call Hydro(...)  
  call other physics  
  .....  
End Do
```

- Each loop iteration advances the solution by **dt**



Grid Unit

- ❑ Overview: Purpose
- ❑ Overview: Implementations
- ❑ Overview: blocks, cells, ...
- ❑ PARAMESH: oct-tree
- ❑ Data structures and Meta-Data
- ❑ Configuring Variables for Grid Data Structures
- ❑ Dimensions and Geometries
- ❑ What the Grid Code Unit Actually Does
- ❑ Using Grid



First Look at Paramesh (and UG) Grids

- ❑ Purpose of the Grid: represent data
 - ❑ Much more on *UNK* variables etc. below
- ❑ Each block of data resides on exactly one processor* (at a given point in time)
- ❑ At a given point in time, the number of local blocks on a processor lies between 1 and MAXBLOCKS. (or even 0, at least in initialization)
 - ❑ Grid_getLocalNumBlks returns the current local value.
 - ❑ MAXBLOCKS is defined at setup time. This represents a hardwired limit on how many blocks can exist in total.
 - ❑ Paramesh attempts to balance blocks across processors so that processor will have approximately equal amounts of work to do.
 - ❑ With the FLASH3 Uniform Grid (UG), the number of blocks is always one per processor.

*By the way, where I say processor, I really mean PE – processing entity (in MPI terminology). The difference? One can distribute across more PEs than physical procs.



Overview: Implementations

- ❑ UG – Uniform Grid
 - ❑ Fast, very little overhead
 - ❑ Use when your problem does not profit from varying resolution
- ❑ Paramesh2 – **old** AMR for FLASH2 compatibility
- ❑ Paramesh4.0 (aka Paramesh3,...)
 - ❑ **Currently default Grid Implementation, recommended**
- ❑ Paramesh4dev
 - ❑ May become the default; **also recommended** to use.
 - ❑ Same functions as PM4.0, users should see no differences in results. (only known exception: very small differences possible with face variables.)
 - ❑ Performance can differ from PM4.0:
 - ❑ Faster in handling grid refinement changes
 - ❑ Other Grid operations may be slightly slower

Simplest way to select: setup shortcut `+ug` *or* `+pm40` *or* `+pm4dev`



More on Paramesh 4dev


PARAMESH Update – if you used Paramesh 3 or 4.0 before:

We now package FLASH with 3 versions of the PARAMESH library:

- ❑ Paramesh2 – for old time's sake (comparison with FLASH2)
- ❑ Paramesh4.0 – as released by K. Olson (some minor modifications)
- ❑ In place of what we used to call “Paramesh3” before FLASH3.1 release
- ❑ Paramesh4dev – currently ~Paramesh4.1
- “LIBRARY mode” is obligatory:
 - ➔ `nxb..nzb`, `ndim`, `maxblocks`, etc. are *runtime* parameters (as far as PARAMESH is concerned!)
 - ➔ Arrays for `unk` (solution data) etc. are dynamically allocated at runtime init
- (b) Rewritten algorithm by K. Olson for generating mesh metainfo after refinement changes
 - ❑ Performance may be degraded (because of (a)) or improved (because of (b)) depending on problem, therefore we are offering both.
 - ❑ Intend to follow further Paramesh development.



Overview: blocks and cells




- ❑ The grid is composed of blocks
- ❑ FLASH3: In current practice, all blocks are of same size.
- ❑ May cover different fraction of the physical domain, depending on a block's resolution.
- ❑ Each, block reserves space for some layers of guard cells.



Overview: blocks, cells, regions



- ❑ Blocks consist of cells: guard cells and interior cells.
- ❑ For purposes of guard cell filling, guard cells are organized into **guard cell regions**.



- ❑ During guard cell filling, each guard cell region may get filled from a different data source:
 - ❑ A local neighbor block
 - ❑ A remote neighbor block
 - ❑ A boundary condition
 - ❑ using data from adjacent interior cells
 - ❑ Using fixed or coordinate-based data
 - ❑ Interpolation from parent (if the block touches a fine/coarse boundary)
- ❑ In PARAMESH4, diagonal regions are treated just like “face-sharing” regions! (not so in PM2)



PARAMESH: An Oct-tree of Blocks



- ❑ Paramesh specific design:
 - ❑ Block Structured
 - ❑ All blocks have same dimensions
 - ❑ Blocks at different refinement levels have different grid spacings and thus cover different fractions of the physical domain
 - ❑ Fixed sized blocks specified at compile time
- ❑ Global **block numbers** are based on Morton order, approximates “space-filling” behavior. (example numbers for PM2; PM4 is very similar.)
- ❑ Storage order within each processor follows this ordering. Re-distribution of blocks after refinement changes, for load balancing.
- ❑ **Oct**-tree in 3D: A node has either 8 children or none. (Quad-tree in 2D, binary in 1D)
- ❑ Blocks are of type **LEAF**, **PARENT**, or **ANCESTOR**.
- ❑ Data for PARENT and ANCESTOR blocks occupies storage space! (not much in 3D)

In choosing Paramesh, the original FLASH code architects chose simplicity of the Paramesh structure over a patch based mesh.



Limits of Paramesh

- ❑ PARAMESH is based on blocks, not general patches.
 - ❑ Limitations imposed by Paramesh:
 - ❑ Same number of cells in all blocks
 - ❑ Same number of guard cell layers in all blocks, all directions
 - ❑ Resolution (“Delta”) of a block changes by multiples of 2.
 - ❑ Resolution of neighbors differs at most by factor of 2.
- (In other words: the local refinement level may change by at most ± 1)



How Blocks are Identified

- ❑ At a given time, a block is **globally** uniquely identified by a pair (*PE*, *BlockID*), where
 - ❑ $0 < PE < numprocs$
 - ❑ $1 < BlockID \leq MAXBLOCKS$
- ❑ **Locally**, *BlockID* is sufficient to specify a block
 - ❑ User code can't directly access remote blocks anyway
- ❑ Morton Numbers provide another way to identify blocks **globally**.
- ❑ The global block number of a block determines the index of the block's data in output files. (checkpoint, plot files) It is not available to user code during run time.



How Blocks are Stored

- ❑ Solution data,
- ❑ per-block meta data,
- ❑ tree information (for local blocks!)

are stored in F90 arrays declared like this:

```
real, dimension(,,,,MAXBLOCKS) :: UNK  
real, dimension(,MAXBLOCKS) :: bnd_box  
integer, dimension(,MAXBLOCKS) :: parent
```

etc. etc.

- ❑ MAXBLOCKS is a hardwired constant (from setup time)
- ❑ “Inactive” (non-leaf) blocks also use storage
- ❑ These structures are internal to the Grid unit **and should not be accessed directly by other code.**
- ❑ Use the appropriate *Grid_something* subroutine calls instead!



Grid Data Structures

- ❑ CENTER
 - ❑ The “normal” way to keep fluid variables: logically cell-centered
 - ❑ Kept internally in an array UNK of dimensions
UNK(NUNK_VARS, NXB+gc, NYB+gc, NZB+gc, MAXBLOCKS)
- ❑ FACEX, FACEY, FACEZ
 - ❑ Face-centered variables, currently used by unsplit MHD solver
 - ❑ Supported in UG, PM 4.0, PM 4dev
- ❑ SCRATCH (*data that is never updated automatically by Grid*)
 - ❑ Additional block-oriented storage provided by FLASH (not PM Kernel)
 - ❑ Guard cell filling or other communications not supported
- ❑ WORK (*only 1 “variable”, not recommended for portability*)
 - ❑ Additional block-oriented storage provided by PARAMESH (not in UG)
 - ❑ Used internally by physics units (currently: multigrid)
- ❑ (FLUX – not a permanent data store, for flux corrections by *Hydro*)



Configuring Variables for Grid Data Structures

- ❑ Use VARIABLE `vvvv` in Config for `unk(VVVV_VAR,::,::,::)**`
 - ❑ `gridDataStruct=CENTER*`
- ❑ Use SPECIES `ssss` in Config for `unk(SSSS_SPEC,::,::,::)`
 - ❑ `gridDataStruct=CENTER`
- ❑ Use MASS_SCALAR `mmm` for `unk(MMMM_MSCALAR,::,::,::)`
 - ❑ `gridDataStruct=CENTER`
- ❑ Use FACEVAR `ffff` in Config for `facevarx(FFFF_FACE_VAR,::,::,::)`, `facevary(FFFF_FACE_VAR,...)`, & `facevarz(FFFF_FACE_VAR,...)`
 - ❑ `gridDataStruct=FACEX/FACEY/FACEZ` (or for some calls: `FACES`)
- ❑ Use GRIDVAR `ggg` for `scratch(:,::,::,GGG_SCRATCH_GRID_VAR,:)`
 - ❑ `gridDataStruct=SCRATCH`

* Many Grid interfaces have a `gridDataStruct` argument to specify what kind of data to act on. Examples: `Grid_getBlkPointer`, `Grid_putBlkData`, `Grid_getBlkIndexLimits`, `Grid_fillGuardCells`. See API documentation of these interface for details.

** The internal organization (order of array indices) is important for code working with block pointers as returned by `Grid_getBlkPointer`.



Configuring Variables for Grid Data Structures II

- ❑ Use VARIABLE *vvv* in Config for `unk(VVV_VAR,::,::,::,::)`
 - ❑ `gridDataStruct=CENTER`
- ❑ Use SPECIES *sss* in Config for `unk(SSSS_SPEC,::,::,::,::)`
 - ❑ `gridDataStruct=CENTER`
- ❑ Use MASS_SCALAR *mmm* for `unk(MMMM_MSCALAR,::,::,::,::)`
 - ❑ `gridDataStruct=CENTER`

Cell-centered variables from VARIABLE, SPECIES, MASS_SCALAR become parts of the same large array:

- ❑ `unk(1:NPROP_VARS,::,::,::,::)` holds *NPROP_VARS* **VARIABLES**
- ❑ `unk(SPECIES_BEGIN:SPECIES_END,::,::,::,::)` holds *NSPECIES* **SPECIES**
 - ❑ Note: often *NSPECIES=0*, in that case *SPECIES_END=SPECIES_BEGIN-1*
- ❑ `unk(MASS_SCALARS_BEGIN:NUNK_VARS,::,::,::,::)` holds *NMASS_SCALARS*

MASS_SCALARS

- ❑ Often *NMASS_SCALARS=0*, in that case *MASS_SCALARS_BEGIN = NUNK_VARS+1*



More On Variables for Grid Data Structures

- ❑ The **VARIABLE** part of unk represents most solution variables
 - ❑ **VARIABLE dens TYPE: PER_VOLUME** – conserved variable per volume-unit
 - ❑ **VARIABLE ener TYPE: PER_MASS** – energy in mass-specific form
 - ❑ **VARIABLE temp TYPE: GENERIC** – not a conserved entity in any form

Specify the **TYPE** correctly to ensure correct treatment in Grid interpolation!
See Config files in included code Units for examples: *Hydro*, *Eos*, ...
- ❑ The **SPECIES** part of unk represents mass fractions
 - ❑ Get automatically advected by *Hydro*
 - ❑ Should probably be used with *Multispecies* Unit and *Multigamma* EOS
 - ❑ Should always add up to 1.0, code may enforce this
 - ❑ Treated as a per-mass variable for purposes of interpolation
- ❑ The **MASS_SCALAR** part of unk represents additional variables
 - ❑ Get automatically advected by *Hydro*
 - ❑ Treated as a per-mass variable for purposes of interpolation



Dimensions and Geometries

Improved Geometry Support

The FLASH3 *Grid* supports these geometries:

- ❑ Cartesian - **1D, 2D, 3D**
- ❑ Cylindrical - **2D**, (3D?)
- ❑ Spherical - **1D**, (2D), (3D)
- ❑ Polar - (2D)

Combinations in **bold** have been extensively used & tested at the FLASH Center.

(Note: for a specific application, geometry support may be limited by available solvers!)

The *Grid* Implementation:

- ❑ Makes use of Paramesh4 support of geometries
- ❑ Centralized support by *Grid* unit, provides routines for cell volumes, face areas, etc.
- ❑ Physics units do not need to have special code for each supported geometry
- ❑ *Grid* uses geometry-aware conservative interpolation at refinement boundaries
 - ❑ This is now default interpolation, internally called “monotonic”.
 - ❑ we provide a way to use an alternative *Grid* implementation's native methods instead:

```
./setup ... -gridinterpolation=native
```



What the Grid Code Unit Actually Does

Note: the following focuses on AMR Grids; UG is simpler.

The Grid unit is responsible for

- ❑ Keeping account of the spatial domain as a whole:
 - ❑ Extent and size, outer boundaries
- ❑ Keeping and maintaining block structure:
 - ❑ Which blocks exist?
 - ❑ Where are they?
 - ❑ Sizes and other properties of blocks
 - ❑ Neighbors
 - ❑ Parent / child links for AMR
- ❑ Initializing block structure:
 - ❑ Initialize the metadata and links mentioned above
 - ❑ Keep Grid structure valid:
 - ❑ Consistent (if A is child of B, then B must be parent of A, etc. etc.)
 - ❑ For PARAMESH: no refinement jumps by more than 1 level



What the Grid Unit Actually Does - Cont.

Note: the previous slide was mostly about meta-data; now about the stuff actually wanted by users...

The *Grid* unit is also responsible for

- ❑ Keeping data (“User data”, “Solution data”, “payload”):
 - ❑ Provide storage
 - ❑ UNK, FACEVAR{X,Y,Z}, SCRATCH, (WORK)
 - ❑ FLUXes and other more temporary arrays
- ❑ Initializing solution data:
 - ❑ Actually left to user, who provides Simulation_initBlock
 - ❑ *Grid* must invoke user function, apply refine criteria, repeat as necessary
- ❑ maintaining and keeping track of data during refinement changes:
 - ❑ Apply refinement criteria as requested
 - ❑ Copy data within processor, and/or communicate between procs
 - ❑ Involves prolongation (interpolation)
 - ❑ Involves restriction (valid data in PARENT blocks)



What the Grid Unit Actually Does - Cont..

Note: the previous slide was about data and mesh changes; now what's left to do between those changes?

- ❑ The *Grid* unit is **also** responsible for
- ❑ Operations that **communicate** user data between blocks:
 - ❑ Prolong (interpolate) data
 - ❑ After new leaf blocks are created
 - ❑ Restrict (summarize) data
 - ❑ PARENT blocks usually get summarized data as part of guard cell filling
 - ❑ Flux correction (special operation invoked from *Hydro*)
 - ❑ Edge averaging (special operation invoked from MHD *Hydro*)

And finally...

- ❑ **Guard cell filling**
 - ❑ The most important form of data communication on an established mesh configuration.
 - ❑ Called frequently, by various code units
 - ❑ May move a lot of data between procs, efficiency is important!



Guard Cell Filling – When

Note: the following focused on Paramesh4, but high-level calls apply to all grids – they may just not do much.)

- ❑ When are guard cells filled?
 - ❑ Directly: High-level call to `Grid_fillGuardCells` (or maybe `amr_guardcell`)
 - ❑ Always a global operation involving all processors
 - ❑ Usually fills guard cells of LEAF blocks and their parents – but don't count on it for PARENT blocks.
 - ❑ Indirectly: internally as part of some other Grid operation
 - ❑ As part of `amr_prolong` (filling new leaf blocks)
 - ❑ Indirectly during global direct filling:
 - ❑ Auxiliary filling of a PARENT block's guard cells in order to provide input for interpolation to this PARENT's child, a finer-resolution LEAF node.



Guard Cell Filling - Usage

When should you fill guard cells?

- ❑ Before a subroutine you wrote uses guard cells, you need to make sure they are filled with valid and current data.
- ❑ FLASH3 does not guarantee that guard cells are valid on entry to a solver, source term code unit, etc.!

❑ How should you fill guard cells?

- ❑ Only worry about direct filling of LEAF guard cells – that is nearly always what is needed.

❑ Basic high-level call:

```
Call Grid_fillGuardCells(myPE,CENTER_FACES,ALLDIR)
```

❑ High-level call with automatic Eos call on guard cells:

```
Call Grid_fillGuardCells(myPE,CENTER_FACES,ALLDIR,doEos=.true.)
```

- ❑ Eos often needs to be called to get cells at refinement boundaries, where data was interpolated, into thermodynamic balance.
- ❑ There are many additional optional arguments, see API docs. They are for increasing performance, and can all be initially ignored.